

ODBC/JDBC Listener for NT™

For NetWare 4.11 and 5.0

Installation Card

This card takes you step by step through the installation of ODBC/JDBC Listener on a computer running Windows NT. For information on Remote ODBC/JDBC drivers, refer to the online reference guide.

Beta Note To access the online reference guide for ODBC/JDBC Manager for NetWare, once this software is installed, run WHSTART.html from a Windows NT client. WHSTART.html is located in ODBC/docs/HTMLHelp folder on the NetWare server where you installed ODBC/JDBC Manager for NetWare software.

System Requirements

- An Intel® 486 or Pentium™ CPU computer with 32 MB of RAM (64 MB recommended)
- Hard disk with 3.1 MB of free space
- CD-ROM drive
- Windows NT 3.51 (NT 4.0 recommended)
- Network adapter
- TCP/IP networking option

- Netscape Navigator 4.05 (or higher) or Internet Explorer 4.0 (or later)

Before you begin...

If you have a previous version of ODBC/JDBC Listener for NT installed on your computer, uninstall it with Add/Remove Programs in the Control Panel *before* you install the new version.

In order to install ODBC/JDBC Listener for NT successfully, you must have Administrator privileges that let you install NT services.

Installing ODBC/JDBC Listener for NT

1. Close all ODBC applications and log on as the administrator who creates system data sources and performs ODBC/JDBC Listener for NT administration.
2. Copy the file you downloaded from the Web to a Windows workstation networked to the NetWare server.
3. From the File menu, choose Run. In the Command Line box, type `x:\ODBC-JDBC_Listener_for_NT_Setup.EXE`, substituting the appropriate drive letter for *x*. Select [OK].
4. The license agreement appears. Select [Accept] to accept the terms and conditions of the License Agreement and proceed with the installation. (If you select [Decline], Setup exits.)
5. The Validate License Key dialog box appears. Enter your organization name. Select [Next].

7. Setup checks for earlier versions of ODBC/JDBC Listener for NT running on the server. If it detects ODBC/JDBC Listener for NT running on the server, you must shut it down before proceeding with Setup.

To stop ODBC/JDBC Listener for NT immediately, select [Yes]. Setup automatically stops ODBC/JDBC Listener for NT and continues.

If you want to stop ODBC/JDBC Listener for NT at a more convenient time for your users, select [No]. Setup exits. You must stop ODBC/JDBC Listener for NT manually before you can install a new version of ODBC/JDBC Listener for NT.

8. The Welcome dialog appears, advising you to close all active Windows applications before you proceed with Setup. Close any active applications, then return to this screen and select [Next].

NOTE If you proceed with Setup and have applications open, you must restart Windows before you can use ODBC/JDBC Listener for NT.

The Setup Installation Directory dialog appears. The preset directory `C:\Novell\ODBC-JDBC Listener for NT` on the drive that Windows is installed on. The dialog box also shows the required and available space on the installation drive.

If you accept the default drive and directory,

skip to step 14.

9. If you want to change the installation drive, select [Disk Space] to view space on a different drive.
10. Select the new drive from the drop-down list of available drives to check disk space available. Select [OK] when you have chosen a suitable installation drive.
11. To change the installation directory, select Browse...
12. In the Path text box, type the drive and directory where you want to install ODBC/JDBC Listener for NT. You can type any pathname you want.
or
Select a directory from the Directories list and a drive from the Drive drop-down list. Select [OK].
13. The new path is displayed in the Select Installation Directory dialog box. Select [Next].
The Select Drivers dialog box appears. By default, ODBC/JDBC Listener for NT installs the Oracle driver onto your system.
14. To specify that a driver not be installed, deselect the check box associated with that driver. Select [Next].
15. The Select Program Folder dialog box appears. To change the Program Folder name, type the new name in the text box or select a different folder from the drop-down list. Select [Next].
16. The Confirm Settings dialog box appears. Review the selections you have made. To make any changes, select [Back] until you return to the dialog box

that contains the settings you want to change. Make the changes, then select [Next] until you return to the Confirm Settings dialog box.

17. Select [Install].

Windows NT 3.51: The ODBC/JDBC Listener for NT program files are copied to your hard drive and the ODBC/JDBC Listener for NT program folder is created on your desktop. ListenerAdmin and ListenerControl icons are placed in this folder, along with Help files, a *Readme* file and an Uninstall utility.

Windows NT 4.0: An ODBC-JDBC Listener for NT program folder is created which can be accessed from the Start menu. The program folder contains ListenerAdmin and ListenerControl icons, along with a *Readme*.

The Setup Complete dialog box appears. When all the files have been successfully copied to your installation directory, Setup checks for the following system prerequisites. You are advised as Setup checks for them.

- TCP/IP networking option
- SQL*Net (optional; only if you installed the Oracle driver)
- Open Client (optional: only if you installed the Sybase driver)

If Setup finds the required system components, the installation is complete and ODBC/JDBC Listener for NT will be started automatically.

If you receive any messages advising you of

problems, consult the troubleshooting section in the documentation, or call Novell Technical Support.

If you had any applications open when you installed ODBC/JDBC Listener for NT, you may need to restart your computer before you can use ODBC/JDBC Listener for NT. Select [Yes] to automatically restart your computer. Select [No] to do so at a later time.

18. Remove disk from your drive. Select [Finish] to exit Setup. ODBC/JDBC Listener for NT starts automatically on your server.

19. Configure data sources. For detailed information about working with data sources, see online documentation for ODBC/JDBC Listener.

20. Configure and install the Remote ODBC Driver. Refer to the installation card for ODBC/JDBC Manager for NetWare.

How to Contact Us

For more information, contact Novell Technical Support.

Web: <http://support.novell.com/>

North America: 1-800-858-4000 or 1-801-861-4000

Japan: +81-3-5481-1050

Asia Pacific: +61-2-9925 3133

© 1999 Novell, Inc. All rights reserved. All trademarks, brands and product names are property of their respective owners.