

Setting Up Novell Small Business Suite 5

Easy to install and manage, Novell® Small Business Suite 5 is a network software system designed to give single-site businesses superior performance and powerful intranet and Internet capabilities.

PREREQUISITES

- ❑ A basic understanding of networking and NDS™. See the “Server Basics” chapter of the NetWare 5 *Overview and Installation* manual. A PDF version of this manual is available in the INSTALL.PDF file located at the root of the *NetWare 5 Server CD 1*.
- ❑ Novell Small Business Suite supports a multiserver environment in which all servers are running the same version of the Novell Small Business Suite product.

MEET SYSTEM REQUIREMENTS

- ❑ For the administrator’s workstation, a Windows* 95/98 or Windows NT* workstation with an installed network board and a working CD-ROM drive.
- ❑ For the server, a PC with a Pentium* 200 MHz or higher processor with
 - A VGA or higher resolution display adapter (SVGA recommended)
 - A working CD-ROM drive
 - A 3.5-inch diskette drive
 - A PS/2* or serial mouse

- One or more installed network boards
- 64 MB of RAM (128 MB is recommended to run Java* applications)
- ❑ Available disk space on the server:
 - New installation: 2 GB of available disk space
 - Upgrade: 35 MB of available disk space on the DOS partition; 1 GB of available disk space on volume SYS.
- ❑ If upgrading, a supported NetWare® operating system:
 - intraNetWare for Small Business
 - NetWare for Small Business 4.11 or 4.2
 - NetWare 3.1x
 - NetWare 4.1x or NetWare 4.2
- ❑ If Internet access is desired, an account with an ISP and supported connection devices available in the server.

SET UP A NETWARE 5 SERVER

1. Back up all data.
2. At the server computer, insert the *NetWare 5 Server CD 1* and the *Pre-installation/License* diskette into the appropriate drives.
3. Reboot the computer.
4. Select a language.
5. Select the type of installation:
 - Express Installation—use to install the first NetWare 5 server or to upgrade other servers to NetWare 5. Express Installation will use 100 MB of server disk space for a DOS partition and all remaining disk space for volume SYS. If your setup needs additional options, use the Custom Installation.
 - Custom Installation—use to perform installations or upgrades that require customization, such as installing a server into an existing NDS tree, selecting device drivers, and selecting partition and volume sizes.
6. Follow the on-screen instructions.

Note

For information about the options provided in the Custom Installation, see the *INSTALL.PDF* file located at the root of the *NetWare 5 Server CD 1*.

SET UP A WORKSTATION FOR THE ADMINISTRATOR

Prerequisite: New server installation or upgrade is complete. Make sure the workstation is running Windows 95/98 or Windows NT.

1. Boot the workstation.
2. Insert the *Novell Client CD 2* into the CD-ROM drive, select the language, and run the applicable Novell Client™ installation.
3. Log in to the server as user Admin with the default password of “admin”.
4. Change the passwords for the NDS user Admin and for the bindery-based user Supervisor.

For the bindery-based user Supervisor, at the network drive DOS prompt enter

LOGIN SUPERVISOR /B

(The Supervisor password is “admin”.)

Then enter

SETPASS

Follow the remaining on-screen prompts.

SET UP THE NETWORK USING QUICK SETUP TASKS

Prerequisite: Before running Quick Setup Tasks in Novell Easy Administration Tool™ (NEAT), make sure the setup of the administrator's workstation is complete. For prerequisites for each task, see the online task descriptions.

1. Log in to the server from the administrator's workstation.
2. From the Quick Setup Tasks screen, complete the following tasks:
 - Set up groups
 - Set up users
 - Set up queue-based printing—additional setup required
 - Set up Internet access—additional setup required
 - Set up the GroupWise® system—can only be run one time

SET UP CLIENT WORKSTATIONS

1. Install the Novell Client software.

For Windows 3.1, Windows 95/98, or Windows NT computers, insert the *Novell Client CD 2*, select the language, and run the applicable Novell Client installation.

For Macintosh* or OS/2* computers, obtain and install the applicable client software. Information for downloading software for these clients can be found at <http://www.novell.com/download>.

2. (Optional) Set up GroupWise on the client by running Start > Applications > Install GroupWise at each client workstation. Before you perform this step, GroupWise must be set up on the server, and the Novell Client software must be set up on the workstation.
3. Install other applications on each workstation. You can do this manually, using the Integrate Applications task in NEAT or using the application icon delivered through ZENworks™.

SET UP NETWORK DIRECTORIES AND FILE SYSTEM (OPTIONAL)

- If desired, set up specific directories for applications or database files.

This can help you to manage access to the applications and files if needed.

- Create additional working directories and give users access to the directories. You can do this using Windows features or NEAT. A home directory is automatically created for each User object that is created.

INSTALL NOVELL AND PARTNER SOLUTIONS (OPTIONAL)

1. Insert the applicable solution CD-ROM and follow the on-screen prompts.
- For additional information about each product, prerequisites, and installation instructions, see the PARTNERS.TXT file located at the root of the *Novell and Partner Solutions* CD.
- For additional integration and optimization information for these products, see the online documentation at <http://www.novell.com/> documentation. Click Novell Small Business Suite.

CONSULT ADDITIONAL DOCUMENTATION

- For more detailed instructions on installing and setting up this product, see the printed *Novell Small Business Suite 5 Installation and Administration* manual.
- For updated documentation and the complete set of extended Novell documentation associated with this product, see <http://www.novell.com/> documentation. Click Novell Small Business Suite.
- To order additional printed documentation or a CD with all available Novell documentation, see <http://www.novell.com/documentation>. Click Order Documentation.
- For technical support information, see <http://support.novell.com>. Click Knowledgebase, Forums, or Additional Support.

COPYRIGHT AND TRADEMARKS

Copyright © 1999 Novell, Inc. All rights reserved.

Novell, NetWare, and GroupWise are registered trademarks of Novell, Inc. in the United States and other countries. Novell Client, NDS, Novell Easy Administration Tool, and ZENworks are trademarks of Novell, Inc.

Macintosh is a registered trademark of Apple Computer, Inc.; Java is a registered trademark of Sun Microsystems, Inc.; Pentium is a registered trademark of Intel Corporation; OS/2 is registered trademark of International Business Machines Corporation; and Windows and Windows NT are registered trademarks of Microsoft Corporation.