

# Installing Novell Clients

The Novell® Client™ Setup utility installs the client software. When you use this utility, you can select the client you want to install from a list of available clients.

## PREREQUISITES

- Long.nam installed on NetWare® servers for long file names in Windows\* 95\* and Windows NT\*
- Connection to a NetWare network
- Applicable server patches installed

## HARDWARE REQUIREMENTS

### Windows 95

- 486 processor or higher
- Minimum 28 MB free disk space
- Minimum 16 MB RAM

### Windows NT 4.0

- Minimum hardware requirements of Windows NT 4.0

### DOS and Windows 3.1x

- 386 processor or higher
- Minimum 15 MB free disk space
- Minimum 8 MB RAM
- A memory manager

## SOFTWARE REQUIREMENTS

One of the following client operating systems:

- Windows 95 with Windows 95 CD-ROM or the Windows .cab files, or
- Windows NT 4.0, or
- A DOS operating system such as:
  - Novell DOS™ 7
  - MS-DOS\* 5.x or 6.x
  - PC-DOS 5.x, 6.x, or 7.0
  - Windows 3.1x or Windows for Workgroups 3.11

## PROCEDURE

**Note:** Documentation explaining network installation methods is available in the NetWare 5™ online documentation CD. This documentation can be viewed on 32-bit workstations.

1. Insert the Z.E.N.works™ CD-ROM.
 

If the Setup utility does not start automatically, run winsetup.exe from the Products directory.
2. Click a language for the installation.
3. Click the platform you want to install.
4. Click the software you want to install.
5. Follow the on-screen instructions.

**SOFTWARE INCOMPATIBILITIES****Windows 95**

- Microsoft\* Client for NetWare networks
- Microsoft file and printer sharing for NetWare networks
- Microsoft Service for Novell Directory Services™
- Novell NetWare workstation shell 3.x (NETX)
- Novell NetWare workstation shell 4.0 and later (VLM™)
- Novell IPX™ ODI™ protocol

**Windows NT**

- Incompatibilities listed in the readme