

ODBC/JDBC Manager for NetWare[™]

For NetWare 4.11 and 5.0

Installation Card

This card takes you step by step through the installation of ODBC/JDBC Manager for NetWare, including the Remote ODBC Driver and Remote JDBC Driver for NetWare and the Oracle Driver for NetWare. For assistance in working with ODBC/JDBC Manager for NetWare, refer to the online reference guide.

Beta Note To access the online reference guide for ODBC/JDBC Manager for NetWare, once the Listener for NT component is installed, run WHSTART.html from a Windows NT client. WHSTART.html is located in ODBC/docs/HTMLHelp folder on the NetWare server where you installed ODBC/JDBC Manager for NetWare.

Before you install

Before you start, make sure the following are ready:

- Server running NetWare 5.0 with at least 128 MB of memory and 600 KB disk space *or* Server running NetWare 4.11 with long name space support, IWSP5B (or later) patch, at least 64 MB of memory and 600 KB of disk space

- (Remote ODBC Driver only) Windows NT server with ODBC/JDBC Listener for NT already installed and running
- Netscape Navigator 4.05 (or higher) or Internet Explorer 4.0 (or later)

To install the Remote ODBC Driver or the Oracle Driver

1. Copy the file you downloaded from the web to a Windows workstation networked to the NetWare server.
2. **Windows 95:** Click [Start] on your toolbar, then Run.
Windows NT: Choose the Run command from the File menu.
3. Enter *x:\ODBC-JDBC_Manager_for_NetWare_Setup.EXE*, where *x* is the drive letter or browse to *setup.exe*, then click OK.
4. Click [Next] when prompted to close all open programs, then [Yes] to accept the license conditions.
5. When prompted for an installation directory, locate the SYS volume of the NetWare server where you want to install the software.
6. From the list of software to be installed, deselect check boxes for any software you don't want installed.
7. If applicable, confirm or change locations for documentation and Remote JDBC Driver.
8. Review your selections. To make any changes, click [Back] to return to any prior screen, or [Next] to return to the review dialog.
9. Click [Next]. The components you

checked will be installed on your NetWare server.

10. Check the "readme" box if desired, and click [Finish].
11. Restart the NetWare server by typing **down** at the console prompt. Once the server is down, type **server** to restart the server.

Component	Default location
ODBC Driver Manager	sys:\odbc
Remote ODBC Driver	sys:\odbc\drivers
Remote JDBC Driver	sys:\odbc\jdbc
Oracle Driver	sys:\odbc\drivers
Configuration Utility	sys:\odbc
Online reference guide	sys:\odbc\docs

Note You can change the installation location of the Remote ODBC Client and ODBC drivers; the default above is only a suggestion. However, the following files must remain in their installation location: ODBC.NLM, ODBCADM.NLM, ODBCRTCF.NLM, ODBCORCF.NLM, ODBCINST.INI in sys:\odbc, and the ODBCSTRT.NCF in sys:\system.

Before contacting Customer Support

To help us help you more effectively, please have the following information ready when you contact us:

- The version of NetWare you're running
- Your ODBC/JDBC Listener product version
- Your license key
- The contents of the *server.ini* and *odbc.ini* files

How to Contact Us

For more information, contact Novell Technical

Support.

Web: <http://support.novell.com/>

North America: 1-800-858-4000 or 1-801-861-4000

Japan: +81-3-5481-1050

Asia Pacific: +61-2-9925 3133

© 1999 Novell, Inc. All rights reserved. All trademarks, brands and product names are property of their respective owners.